

## Installing the ST-1 application and ST-1 token on a Windows PC

### The ST-1 soft token consists of the following components:

1. CRYPTOCARD ST-1 Application Installation File (**setup-st.exe**, or similar); Account Management Office has informed you of the location of the file.
2. CRYPTOCARD ST-1 Token Configuration file (<username>.tok), provided to you already by the Account Management Office.
3. An initial PIN, provided to you already by the Account Management Office.

### Versions of the ST-1 Application Installation File:

**PRIOR to July 2002:** Version: **5.0** Filename: **setup-st50.exe**

**AFTER July 2002:** Version: **5.16** Filename: **setup-st1.exe**

### Uninstalling your previous ST-1 Application:

A newer version of the ST-1 application (Version 5.16) became available in July 2002. *If you already had an ST-1 application installed on your PC PRIOR TO July 2002*, and you received a new <username>.tok file *during or after July 2002*, you will need to check the appropriate BNL website for a more recent version of the ST-1 application and if one exists, you will need to UNINSTALL the earlier version of the ST-1 (Version.5.0) and then install the new ST-1 Version 5.16 in its place. Use your PC's **Control Panel | Add/Remove Programs** or equivalent in order to uninstall the previous Version of the ST-1; then continue with the following installation instructions to install the V.5.16 ST-1.

### To install the ST-1 on your PC:

- ❑ Download the **setup-st.exe** file from the specified location to your computer and double click it to install it, following recommended default location for install.
- ❑ Place the file called <username>.tok in any directory of your choice on your hard drive, or in the recommended folder **Program Files\CRYPTOCARD\CRYPTOCARD ST-1**
- ❑ Start the ST-1 soft token application from the **Start** menu. A graphical representation of the token will appear. The token will automatically be selected as the current window.

- ❑ Click **File | Programs** on the ST-1 application. Select the <username>.tok file and click **Open**. This will load the token information into the token application.
- ❑ Click **ON** button to activate token.
- ❑ Enter default PIN; choose a New PIN and then verify the New PIN. Click **OK**.

### \*\*\* Replacing/Updating Tokens \*\*\*

If the Account Management Office sends you a new <username>.tok file to replace one already in use in your ST-1 application, simply reload the token by clicking **File | Program**, choose the new <username>.tok file and Click **Open**. When you use the new token, you will again be prompted for a new PIN.

It's also a good idea to make sure you are running the most recent version of the ST-1 application. With the ST-1 open on your desktop, Click **Help | About** to see what version token you are running; then check the ST-1 applications currently available on the appropriate BNL website to verify you are up-to-date. If not, follow the instructions above, starting at "Uninstalling your previous ST-1 Application".